

The interface models the object as a set of input streams and a set of output streams each identified by a 0-based index.

The DMO\_MEDIA\_TYPE structure is used to identify all types of multimedia data.

## IMediaObject methods and structures

Data buffers are wrapped inside an IMediaBuffer interface, a pointer to which is stored in each of the below structures. The IMediaBuffer interface contains a few simple methods to access the data pointer and the buffer's length:

```
interface IMediaBuffer : IUnknown
{
    HRESULT SetLength(
        [in] DWORD cbLength
    );
    HRESULT GetMaxLength(
        [out] DWORD *pcbMaxLength
    );
    HRESULT GetBufferAndLength(
        [out] BYTE **ppBuffer, // not filled if NULL
        [out] DWORD *pcbLength // not filled if NULL
    );
}
```

### DMO\_MEDIA\_TYPE

```
{
    GUID    majortype;
    GUID    subtype;
    BOOL    bFixedSizeSamples;
    BOOL    bTemporalCompression;
    ULONG   lSampleSize;
    GUID    formattype;
    IUnknown *pUnk;
    ULONG   cbFormat;
    BYTE *pbFormat;
}
```

This defines the media type structure. This structure exactly matches the DirectShow AM\_MEDIA\_TYPE structure and is given here for reference.

00000000-0000-0000-0000-00000000

DMO\_OUTPUT\_DATA\_BUFFER

```
{
    IMediaByffer    *pBuffer;
    DWORD           dwFlags;
    REFERENCE_TIME  rtTimeStamp;
    REFERENCE_TIME  rtTimeLength;
}
```

**pBuffer**                      Pointer to buffer wrapper interface  
Can be NULL

**dwFlags** (out)

This must be a combination of the following flag values (or 0)

- DMO\_OUTPUT\_DATA\_BUFFERF\_TIME  
    **rtTimeStamp** is valid
- DMO\_OUTPUT\_DATA\_BUFFERF\_TIMELENGTH  
    **rtTimeLength** is valid
- DMO\_OUTPUT\_DATA\_BUFFERF\_INCOMPLETE  
    Another buffer is required to continue process the input
- DMO\_OUTPUT\_DATA\_BUFFERF\_SYNCPOINT  
    Syncpoint at the beginning of the data<sup>1</sup>

**rtTimeStamp**                  Start time  
**rtTimeLength**                Length

**HRESULT GetStreamCount(DWORD \*pcInputStreams, DWORD \*pcOutputStreams)**

Returns the number of each type of stream. It is possible for objects to have no input streams or no output streams.

**Parameters**

**pcInputStreams**                  Number of input streams  
**pcOutputStreams**                Number of output streams

**Return Values**

**S\_OK**                                  Success  
**E\_POINTER**                            One of the parameters was NULL  
Failure code                            Some other failure

<sup>1</sup> Implicit syncpoints (e.g., regularly occurring syncpoints in an audio stream) must be reflected by this flag. In addition, audio buffers must always begin at a syncpoint.

00629289-073100

**HRESULT GetInputStreamInfo(DWORD dwInputStreamIndex, DWORD \*pdwFlags)**

Returns information about an input stream. This information does not change for the lifetime of this stream.

**Parameters**

<b>dwInputStreamIndex</b>	Zero based index of input stream
<b>pdwFlags</b>	DMO_INPUT_INFOF_HOLDS_BUFFERS The Media Object may hold on to multiple input buffers for this stream

**Return Values**

S_OK	Success
E_POINTER	<b>pdwFlags</b> was NULL
DMO_E_INVALID_STREAM	Stream index out of range
Failure code	Some other failure

**HRESULT GetOutputStreamInfo(DWORD dwOutputStreamIndex, DWORD \*pdwFlags)**

Returns information about an output stream. This information does not change for the lifetime of this stream.

**Parameters**

<b>dwOutputStreamIndex</b>	Zero based index of output stream
<b>pdwFlags</b>	DMO_OUTPUT_STREAMF_WHOLE_SAMPLES Output contains complete samples
	DMO_OUTPUT_STREAMF_SINGLE_SAMPLE Output contains 1 sample
	DMO_OUTPUT_STREAMF_FIXED_SAMPLE_SIZE Output samples are fixed size
	DMO_OUTPUT_STREAMF_DISCARDABLE Output can be discarded in <b>ProcessOutput</b>
	DMO_OUTPUT_STREAMF_OPTIONAL Processing this stream is optional

**Return Values**

S_OK	Success
E_POINTER	<b>pdwFlags</b> was NULL
DMO_E_INVALID_STREAM	Stream index out of range
Failure code	Some other failure

**HRESULT GetInputType(DWORD dwInputStreamIndex, DWORD dwTypeIndex, DMO\_MEDIA\_TYPE \*pmt)**

Get the **dwTypeIndex** type for the input stream **dwInputStreamIndex**. The Media Type returned in **pmt** will be overwritten if the method is successful. The format block of the Media Type must be freed by calling **CoTaskMemFree()**. Often input types will contain a NULL format block.

00620209-073100

The types are enumerated in preference order with the most preferred type corresponding to a type index of 0.

If the call is successful the caller should free the output media type by calling **MoFreeMediaType()** when it's done.

For convenience of implementation it's possible that some types will be enumerated which will fail when used in **SetOutputType()**.

**Parameters**

<b>dwInputStreamIndex</b>	Zero based input stream index
<b>dwTypeIndex</b>	Zero based type index
<b>pmt</b>	Pointer to Media type to return

**Return Values**

<b>S_OK</b>	Success
<b>S_FALSE</b>	Type index out of range
<b>DMO_E_INVALID_STREAM</b>	Stream index out of range
<b>E_OUTOFMEMORY</b>	Could not allocate format block or some other memory failure
Failure code	Some other failure

**HRESULT GetOutputType(DWORD dwOutputStreamIndex, DWORD dwTypeIndex, DMO\_MEDIA\_TYPE \*pmt)**

Get the **dwTypeIndex** type for the output stream **dwOutputStreamIndex**. The Media Type returned in **pmt** will be overwritten if the method is successful. The format block of the Media Type must be freed by calling **CoTaskMemFree()**.

The types are enumerated in preference order with the most preferred type corresponding to a type index of 0.

If the input type is not set for some input stream this call may fail or return a type with a NULL format block.

If the call is successful the caller should free the output media type by calling **MoFreeMediaType()** when it's done.

For convenience of implementation it's possible that some types will be enumerated which will fail when used in **SetOutputType()**.

**Parameters**

<b>dwOutputStreamIndex</b>	Zero based output stream index
<b>dwTypeIndex</b>	Zero based type index
<b>pmt</b>	Pointer to Media type to return

**Return Values**

<b>S_OK</b>	Success
<b>S_FALSE</b>	Type index out of range
<b>DMO_E_INVALID_STREAM</b>	Stream index out of range

00000000-0000-0000-0000-00000000

**E\_OUTOFMEMORY**

Could not allocate format block or some  
other memory failure  
Some other failure

Failure code

**HRESULT SetInputType(DWORD dwInputStreamIndex, const DMO\_MEDIA\_TYPE  
\*pmt, DWORD dwFlags)**

Set a Media Type for an input stream. This call is processed in the context of the types  
currently set for other streams.

**Parameters****dwInputStreamIndex**

Zero based input stream index

**pmt**

Type to set

**dwFlags**

This must be a combination of the following  
flag values (or 0)

**DMO\_SET\_TYPEF\_TEST\_ONLY**

Just check if this type can be set, do  
not set it

**DMO\_SET\_TYPEF\_CLEAR**

Clears the type so that no type is set  
for this stream

**Return Values****S\_OK**

Type was set

**S\_FALSE**

Type cannot be set

**DMO\_E\_TYPE\_NOT\_ACCEPTED**

Type is not acceptable

Failure code

Some other failure

**E\_INVALIDARG**

Invalid argument

**HRESULT SetOutputType(DWORD dwOutputStreamIndex, const  
DMO\_MEDIA\_TYPE \*pmt, DWORD dwFlags)**

Set a Media Type for an output stream. This call is processed in the context of the types  
currently set for other streams.

**Parameters****dwOutputStreamIndex**

Zero based output stream index

**pmt**

Type to set

**dwFlags**

This must be a combination of the following  
flag values (or 0)

**DMO\_SET\_TYPEF\_TEST\_ONLY**

Just check if this type can be set, do  
not set it

**DMO\_SET\_TYPEF\_CLEAR**

Clears the type so that no type is set  
for this stream

**Return Values****S\_OK**

Type can be set

00000000-0000-0000-0000-00000000

S\_FALSE  
 DMO\_E\_TYPE\_NOT\_ACCEPTED  
 Failure code

Type cannot be set  
 Type is not acceptable  
 Some other failure

### **HRESULT GetInputCurrentType(DWORD dwInputStreamIndex, DMO\_MEDIA\_TYPE \*pmt)**

Get the Media Type for an input stream.

If the call is successful the caller should free the output media type by calling **MoFreeMediaType()** when it's done.

#### **Parameters**

<b>dwInputStreamIndex</b>	Zero based input stream index
<b>pmt</b>	Type returned here The type must be freed by calling <b>MoFreeMediaType()</b> if this call was successful

#### **Return Values**

S_OK	Type was returned
DMO_E_TYPE_NOT_SET	Type is not set
E_OUTOFMEMORY	Format block could not be allocated
Failure code	Some other failure

### **HRESULT GetOutputCurrentType(DWORD dwOutputStreamIndex, DMO\_MEDIA\_TYPE \*pmt)**

Get the Media Type for an output stream.

If the call is successful the caller should free the output media type by calling **MoFreeMediaType()** when it's done.

#### **Parameters**

<b>dwOutputStreamIndex</b>	Zero based output stream index
<b>pmt</b>	Type returned here The type must be freed by calling <b>MoFreeMediaType()</b> if this call was successful

#### **Return Values**

S_OK	Type was be set
DMO_E_TYPE_NOT_SET	Type is not set
E_OUTOFMEMORY	Format block could not be allocated
Failure code	Some other failure

007E2D" 69262960



This method should be called after the types of all streams have been set using **SetInputType()** and **SetOutputType()**.

```
(*pcbMaxLookahead + 2 * (dwBufferSize - 1)) / dwBufferSize
```

## Parameters

Zero based input stream index

**Returns** buffer size

Maximum size of data held by this object if it  
AddRefs multiple input buffers  
Or 0.

Returns buffer alignment. 1 means no alignment requirement.

S\_OK  
E\_POINTER  
Failure code

**Call successful**

NULL pointer passed in

**Other failure**

**Get buffer size and alignment requirements for a given output stream.**

This method should be called after the types of all streams have been set using **SetInputType()** and **SetOutputType()**.

**dwOutputStreamIndex**  
**pcbSize**  
**pdwAlignment**

Zero based output stream index

**Returns buffer size**

**Returns buffer alignment.** 1 means no alignment requirement.

```
S_OK
E_POINTER
```

Call successful

NULL pointer passed in



### Other failure

Notifies the Media Object that the data is discontinuous on input stream **dwInputStreamIndex**. This can occur (for example) because there is a large gap in the data, because no more data is expected, or because the format of the data is changing.

The Media Object should generate all output which can be generated from the data already received in calls to **ProcessInput()** on this stream before accepting more data on this stream.

Calling **Discontinuity()** more than once without intermediates call to **ProcessInput()** is equivalent to calling **Discontinuity()** once.

If the **Discontinuity()** method has been called on all input streams for a Media Object and all output has been processed from all the output streams by calls to **ProcessOutput()** then the Media Object is in the equivalent state to the flushed state. In this state all buffers must be released and no more output can be generated until **ProcessInput()** is called again. Also in this state calling **Flush()** has no effect.

## Parameters

<b>dwInputStreamIndex</b>	0-based input stream index
---------------------------	----------------------------

## Return Values

S OK                      Call was successful

## HRESULT Flush()

Flush internally buffered data and reset any streaming state. Media types and other parameters such as latency are not changed.

**All Media Buffers held by all streams must be released on return from this call. Any incomplete processing of a discontinuity for any input stream is cancelled.**

**All streams should accept input after a `Flush()` call.**

## Parameters

## Return Values

S_OK	Successful
Failure code	Failure



**HRESULT AllocateStreamingResources()**

Hint to allocate any resources necessary for processing. This method may not be called before the first call to **ProcessOutput()** and it is not required to support this method.

**Parameters****Return Values**

S_OK	Successful. Return this if the call is not implemented.
Failure code	Some failure occurred

**HRESULT FreeStreamingResources()**

Hint to free any resources necessary for processing.

**Parameters****Return Values**

S_OK	Successful. Return this if the call is not implemented.
Failure code	Some failure occurred

**HRESULT GetInputStatus(DWORD dwInputStreamIndex, DWORD \*pdwFlags)**

Return input stream status.

**Parameters**

dwInputStreamIndex	0-based input stream index
pdwFlags	DMO_INPUT_STATUSF_ACCEPT_DATA This stream is ready to accept data

The setting of this flag can only change as the result of one of the following calls:

**ProcessOutput()**  
**Discontinuity()**  
**ProcessInput()**  
**Flush()**

**Return Values**

00000000-0000-0000-0000-00000000

**HRESULT ProcessInput(DWORD dwInputStreamIndex, IMediaBuffer \*pBuffer, DWORD dwFlags, REFERENCE\_TIME rtTimeStamp, REFERENCE\_TIME rtTimeLength)**

Deliver an input buffer for a stream. The Media Object should either process all the data inside this method or call **IMediaBuffer::AddRef()** to hold the buffer waiting for calls to **ProcessOutput()**. When the Media Object has generated all the output it can from this buffer it should call **IMediaBuffer::Release()** unless it needs the buffer for lookahead.

If the Media Object calls **IMediaBuffer::AddRef()** the application should not reuse a buffer until the matching **IMediaBuffer::Release()** is called.

#### Parameters

<b>dwInputStreamIndex</b>	Zero based input stream index
<b>pBuffer</b>	Buffer containing data Cannot be NULL
<b>dwFlags</b>	Must be a combination of the following flag values (or 0) <b>DMO_INPUT_DATA_BUFFERF_TIME</b> <b>rtTimeStamp</b> is valid <b>DMO_INPUT_DATA_BUFFERF_TIMELENGTH</b> <b>rtTimeLength</b> is valid <b>DMO_INPUT_DATA_BUFFERF_SYNCPOINT</b> Syncpoint at the beginning of the data
<b>rtTimeStamp</b>	Start timestamp in 100ns units
<b>rtTimeLength</b>	Length in 100ns units

#### Return Values

<b>S_OK</b>	Processed normally
<b>S_FALSE</b>	No output.
<b>DMO_E_NOTACCEPTING</b>	Data cannot be accepted until previous output has been processed by calling <b>ProcessOutput()</b>

**HRESULT ProcessOutput(DWORD dwReserved, DWORD cOutputBufferCount, DMO\_OUTPUT\_DATA\_BUFFER \*pOutputDataBuffers, DWORD \*pdwStatus)**

Generate outputs from current input data. The status fields in the output data buffers are updated as a result of this call.

The **IMediaBuffer** pointers in the **DMO\_OUTPUT\_DATA\_BUFFER** structures should not be held by **AddRef** after return from this call (ie their reference counts should be the same on exit as on entry).

Output buffer status fields are undefined if this call returns a failure code.

After calling **ProcessOutput()** the application should check all output streams for the **DMO\_OUTPUT\_DATA\_BUFFERF\_INCOMPLETE** flag. It is possible, for instance, when there are multiple output streams, for a stream which did not report **DMO\_OUTPUT\_DATA\_BUFFERF\_INCOMPLETE** previously to report it after a subsequent call to **ProcessOutput()**.

00629289-073100

Parameters

<b>dwFlags</b>	DMO_PROCESS_OUTPUT_DISCARD_WHEN_NO_BUFFER If the pBuffer member of one of the output buffer structures is NULL discard output data.
<b>cOutputBufferCount</b>	Count of input buffers - this should be the same as the number of output streams.
<b>pOutputDataBuffers</b>	Array of output data buffers of size cOutputBufferCount.
<b>pdwStatus</b>	The Media Object should return 0 here.

Return Values

<b>S_OK</b>	Processing was successful
Failure code	Failure in processing

**HRESULT GetInputMaxLatency(DWORD dwInputStreamIndex, REFERENCE\_TIME \*prtMaxLatency)**

Returns the maximum latency in time between input on the stream and the corresponding output timestamps. Thus, for example, if input timestamped at time T generates output for time T-Delta then this value is the maximum possible value of Delta for the media types defined. This value does not take into account input buffer size.

Parameters

<b>dwInputStreamIndex</b>	0-based input stream index
<b>prtMaxLatency</b>	Latency

Return Values

<b>E_NOTIMPL</b>	Not implemented. Assume 0 latency
<b>S_OK</b>	OK
Failure code	Failure

**HRESULT SetInputMaxLatency(DWORD dwInputStreamIndex, REFERENCE\_TIME rtMaxLatency)**

Sets the maximum latency in time between input on the stream and the corresponding output timestamps. Thus, for example, if input timestamped at time T generates output for time T-Delta then this bounds the maximum possible value of Delta for the media types defined. This value does not take into account input buffer size.

Parameters

<b>dwInputStreamIndex</b>	0-based input stream index
<b>prtMaxLatency</b>	Latency

Return Values

<b>E_NOTIMPL</b>	Not implemented. Latency cannot be set.
<b>S_OK</b>	OK
<b>E_FAIL</b>	Latency cannot be set

00000000-0000-0000-0000-00000000

**HRESULT Lock(LONG lLock)**

Acquire a lock so that multiple operations can be performed while keeping the Media Object serialized.

**Parameters**

<b>lLock</b>	<b>TRUE</b> – lock
<b>prtMaxLatency</b>	<b>FALSE</b> - unlock Latency

**Return Values**

<b>S_OK</b>	<b>OK</b>
<b>E_FAIL</b>	<b>Cannot lock</b>

**Registration****DMO\_PARTIAL\_MEDIATYPE**

```
{
    GUID type;
    GUID subtype;
}
```

<b>type</b>	Major type for matching corresponding media types GUID_NULL means match any type
<b>subtype</b>	Subtype for matching corresponding media types GUID_NULL means match any subtype

**HRESULT DMORegister(LPCWSTR szName, REFCLSID rclsidDMO, REFGUID rguidCategory, DWORD dwFlags, DWORD cInTypes, const DMO\_PARTIAL\_MEDIATYPE \*pInTypes, DWORD cOutTypes, const DMO\_PARTIAL\_MEDIATYPE \*pOutTypes)**

Register a new object, its category and the media types it supports.

**Parameters**

<b>szName</b>	Registration name for this DMO. Names longer than 79 characters may be truncated.
<b>rclsidDMO</b>	Class ID the corresponding COM object for the DMO is registered under.
<b>rguidCategory</b>	Class ID the corresponding COM object for the DMO is registered under.
<b>dwFlags</b>	Category of this object This must be a combination of the following flag values (or 0).
<b>cInTypes</b>	<b>DMO_REGISTERF_IS_KEYED</b> Object use is restricted to by key Number of input types to register

00629209-073100

**plnTypes**  
**cOutTypes**  
**pOutTypes**

Input types  
Number of output types to register  
Output types

**Return Values**

**HRESULT DMOUnregister(REFCLSID rclsidDMO, REFGUID rguidCategory)**

Unregister a media object from one or all categories.

**Parameters**

<b>rclsidDMO</b>	Class ID of the DMO
<b>rguidCategory</b>	Remove from this category If this is GUID_NULL unregister this object from all categories

**Return Values**

**HRESULT DMOEnum(REFGUID rguidCategory, DWORD dwFlags, DWORD cInTypes, const DMO\_PARTIAL\_MEDIA\_TYPE \*pInTypes, DWORD cOutTypes, const DMO\_PARTIAL\_MEDIA\_TYPE \*pOutTypes)**

Enumerate Media Objects by category and/or by media type. GUID\_NULL means match any GUID.

**Parameters**

<b>rclsidDMO</b>	Class ID the corresponding COM object for the DMO is registered under.
<b>rguidCategory</b>	Category of this object
<b>dwFlags</b>	This must be a combination of the following flag values (or 0).  <b>DMO_REGISTERF_INCLUDE_KEYED</b> Include keyed objects
<b>cInTypes</b>	Number of input types to register
<b>plnTypes</b>	Input types
<b>cOutTypes</b>	Number of output types to register
<b>pOutTypes</b>	Output types

**Return Values**

**Media Type helpers**

Use these functions to manipulate media types.

00629289-073100  
DOT E20" 68262960



Where to allocate the new media type  
Size of format block

## E\_OUTOFMEMORY

Delete a media type allocated by **MoCreateMediaType** or **MoDuplicateMediaType()** or returned by pointer from an API or interface method.

**pmt** Media type to delete

**SULT MoDupliateMediaType(DMO\_MEDIA\_TYPE \*\*ppmtDest, const  
\_MEDIA\_TYPE \*pmtSrc)**

## Parameters

<b>ppmtDest</b>	New type
<b>pmtSrc</b>	Source

## E\_OUTOFMEMORY

090603020